




Install and set up the app

Open the directory 4. Tutorial_Arduino\5_APP and install " btcontroller .apk " to the Android phone

Y072\4. Tutorial_Arduino\5_APP

名称	修改日期	类型
 btcontroller.apk	2022/7/25 10:01	APK 文件
 btcontroller.rar	2022/8/22 15:30	WinRAR 压缩文件
 How to use APP.docx	2022/7/30 14:43	DOCX 文档

Next , we use an Android phone to demonstrate how to control the ZHIYI intelligent robotic arm car through this application:

Enter the professional debugging interface, click the add button "+"



You need to fill in the project name of the project name.

+ 添加调试工程

工程名称:
mypro

工程类型:

☐ 竖屏视图

☒ 横屏视图

取消 确定

Click OK to see the built project

Tx: 0B/s Rx: 0B/s Err: 0B/s



mypro
今天 18:09打开过



Click on the project name and the option to modify the project will appear



First configure the communication settings , click the "+" sign, add a boolean value , and enter the boolean value name.





You can see that the created Boolean values will be arranged and displayed in this column, and 11 Boolean value variables will be created in the same way. Tracking, Avoid, follow, dungeon, save, auto, empty, claws_open, claws_closed, count-clockwise, clockwise



Click the "+" sign in the byte value column, add the byte value "byte" , and enter the byte value name




Take setting a variable X that controls the direction of left and right movement as an example, change the name to X



You can see that the created byte values will be arranged and displayed in this column, and use the same method to create 4 byte value variables. respectively Y, speed, Base, Arm



Click the second option at the bottom to create two received byte values, namely: Distance, Actions



After all the above are added, return to the layout " Edit Controls " to add controls .



Click the "+" sign in the upper right corner to create a new control, taking the slider control for speed control as an example;



Select the data type to be connected and the variable value just set, byte and speed



Then set the upper and lower limits, click OK to complete;



Add a joystick control to control the direction of the car:




Select the connection data type byte and the variable name X/Y , then check Release Auto Reset :



Add another same joystick control to control the opening and closing of the paw, the variables are Base and Arm

Add a text control to display the ultrasonic distance :



Add Actions in the same way;



Next, add a control button and click the green button in the upper right corner to link the data:



设定按下时的数值:

1


设定松开时的数值:

0

如果输入框中数据为空, 则在相应时刻变量值不会改变。

OK

Add 11 more controls in the same way : tracking , Avoid, follow, dungeon, save, auto, empty, claws_open, claws_closed, count-clockwise, clockwise. Please drag and place these controls in your own way.



The functions of each icon button in the upper right corner of the screen:

1 Add various controls,

2 Connection variables

3 means setting control parameters

4 is to delete the control

5 Exit the current control layout

6 Mobile controls

7 Zoom in and zoom out controls

8 control rotation angle

When the controls are all adjusted, start connecting to Bluetooth, go to Device Connections and click Search.

Find " JDY-31-SPP " and click "Add Device". If a password is required, enter the password as 1234 or 0000. (If you find that connecting to Bluetooth is slow in future use, first "forget" the Bluetooth in the phone settings. Then search for and connect to Bluetooth in the APP.)

Click "+" again



When a red "x" appears, it means the Bluetooth connection is successful :



After the connection is successful, click Start and operate the car :



The final operation interface is as follows



Notice:

In free mode, the ultrasonic detection distance can be displayed in real time, and other modes are not displayed in real time;

Other modes are automatic execution, and if you want to stop, you need to switch back to free mode;

During operation, pay attention to observe that the servo motor cannot be left in the unfinished state for a long time to prevent heat generation and damage;

Memory function operation: (every time a servo motor is remotely controlled, one action must be saved, and a maximum of 19 steps can be recorded)

The initial robot arm state is remotely controlled to state 1, and the save button is pressed to record 1;

In the remote control from state 1 to state 2, press the save button to record 2;

Remote control from state 2 to state 3, and then press the save button to record 3;

In this way, to the end action, it should be noted that the end action should be consistent with the initial action, so that a continuous and consistent action can be maintained when starting the automation execution.